

Bit nb	Name	Description
0	OPC – <i>Operation Complete</i>	All operation have been completed
1	RQC – <i>Request Control</i>	Ready to control the system (concerns the system based on IEEE-488 bus).
2	QYE – <i>Query Error</i>	Query error detected – exchange message protocol violation. Set to 1 in case: <ul style="list-style-type: none"> - not reading response from a device before sending a new program message, - empty output buffer read, - filled input ot output buffers.
3	DDE (<i>Device Dependend Error</i>)	Device error detected (for example typical operation not completed)
4	EXE – <i>Execution Error</i>	Command execution error detected. Syntacically correct command can't be executed in the state the device entered.
5	CME – <i>Command Error</i>	Command error detected (for example not correct command).
6	URQ – <i>User Request</i>	User request (for example request signaled by pressing the special button on a device user panel)
7	PON – <i>Power-On</i>	Signalling of switching off and on device power from the last read or clear standard event status register.